



- (1) 相应网站上下载符合自己操作系统的客户端:  
官网 <https://www.nomachine.com/download> 或  
神马网页 [http://hpc.ipp.ac.cn/?page\\_id=408](http://hpc.ipp.ac.cn/?page_id=408)
- (2) 安装后打开 nomachine 客户端，点击途中“New”图标:




- (3) 选择 NX 选项，continue:




Select the protocol to use to connect to the remote computer.



- (4) 输入下图的 host 和 port:



Insert the hostname or IP and port where you want to connect.



Tips: 若是 openvpn 连接，host: 10.8.0.1，port: 4022)

(5) continue:

## New connection

NOMACHINE



Choose which authentication method you want to use.



- Password**  
Use password authentication.



- Private key**  
Use key-based authentication with a key you provide.



- Kerberos**  
Use Kerberos ticket-based authentication.

Back

Continue



## New connection

NOMACHINE



Use a HTTP proxy for the network connection.



- Don't use a proxy**  
Choose this if you are connecting to a computer on your same LAN or if you are on a residential broadband connection.



- Connect using a HTTP proxy**  
Use a proxy if you are connecting to a computer outside your LAN from a corporate network where external access is protected by a firewall.

Back

Continue



(6) 为新连接设置 name，并且创建桌面连接：

## New connection

NOMACHINE



Give a name to your connection. Your settings will be saved with this name.



Name

Create a link on the desktop

Back

Done

(7) 连接上面创建的图标:

## Verify host authenticity

NOMACHINE



The authenticity of host shenma.ipp.ac.cn:4022, 202.127.204.22:4022, can't be established. The certificate fingerprint is: 8C D1 1C D7 7B 63 E1 CA 56 7E 78 78 8D 20 D6 90 A3 EB BE C5. Are you sure you want to continue connecting?

No

Yes



(8) 输入神马账号和密码（为了安全，请尽量不要选择 save password），选择 create a new virtual desktop，便可连接到神马登陆节点上

## Connection to 202.127.204.22

NOMACHINE

View Sort Find a type My desktops New desktop

Create a new virtual desktop

Create a new RDP virtual desktop

Create a new custom session

Save this setting in the connection file

Back

Continue

ENTERPRISE SERVER



(9) 神马集群由四个登陆节点，每次连接会随机分配任何一个节点给用户；因 nomachine 是远程图形登陆工具，登陆后的桌面和真实的 linux 操作系统桌面类似。桌面上点击右键，选择“open in terminal”便可打开一个 terminal 窗口

NoMachine - Connection to 202.127.204.22

Applications Places System

Computer

liuxj's Home


Trash

```
liuxj@login112:~/Desktop
File Edit View Search Terminal Help
[liuxj@login112 Desktop]$
```

(10) 退出:

(a) 左上角 system——logout username，完全退出此次连接

(b) 如果需要保留此次连接，以便下次登录时候继续显示该连接，可之间选择右上角的 X 号，关闭当前窗口，下次再次连接时候，会出现下图中“conection to.....”，这是之前的连接记录，选择该图标，点击连接，便可连接到上次保留的连接窗口



Tips:

- (a) 每次连接成功，会在右上角窗口出现一提示小窗口，以使用户知晓集群的一些紧急通知或者常用信息
- (b) 图中红色的 IM 图标，可帮助对连接窗口进行一些设置，比如传输文件，设置窗口分辨率，查看连接节点信息等

